

Standard roles and bootstrap users in PRIME

This article describes the standard roles and bootstrap users that are available in the base configuration package of PRIME.

Related information

See the following links:

- [Nexus PRIME](#)
- [Users and roles](#)

Standard roles

The standard package of Nexus PRIME provides a set of predefined standard roles that can be used as is or adapted to your requirements. This table lists the standard roles and what rights they have in PRIME Designer and PRIME Explorer respectively.

Role	Description	Rights	Technical reference
Bootstrap administrator	Does the initial configuration of PRIME.	PRIME Designer: All PRIME Explorer: Admin	BaseRoleBootstrapAdmin
Policy administrator	A user in Designer.	PRIME Designer: All PRIME Explorer: No	BaseRolePolicyAdmin
Service administrator	Makes configurations in Explorer, such as: <ul style="list-style-type: none">• Start, restart and stop services• Create tenant• Configure connector• Audit the system log and the process lists• Kill processes	PRIME Designer: No PRIME Explorer: Admin	BaseRoleServiceAdmin
Registration officer	Manages "target" users and identities, who are targets (or objects) of credential management actions.	PRIME Designer: No PRIME Explorer: All	BaseRoleRegistrationOfficer
Approver	Approves card production.	PRIME Designer: No PRIME Explorer: Open Tasks	BaseRoleOfficer
Card production administrator	<ul style="list-style-type: none">• Produces cards• Repeats production	PRIME Designer: No PRIME Explorer: Extended Search, Batch Orders	BaseRoleProductionAdmin
Issuing authority	Activates and issues card to requester/user.	PRIME Designer: No PRIME Explorer: Extended Search	BaseRoleIssuingAuthority
User administrator	<ul style="list-style-type: none">• Manages users and identities• Assigns and de-assigns roles to users	PRIME Designer: Roles, User Administration PRIME Explorer: Extended Search	BaseRoleUserAdmin
Helpdesk	<ul style="list-style-type: none">• Resets passwords• Activates and reactivates PRIME users	PRIME Designer: No PRIME Explorer: Extended Search, Open Tasks	BaseRoleHelpdeskOfficer

Self-service user	<ul style="list-style-type: none"> Registers and deregisters herself in the system Registers security password Resets her own password Changes pin Unblocks pin Renews her own card Locks her own card 	PRIME Designer: No PRIME Explorer: No	BaseRoleSelfServiceUser
Self-service visitor	<ul style="list-style-type: none"> Accepts or denies meeting invitation Invites further participant to an existing meeting 	PRIME Designer: No PRIME Explorer: No	BaseRoleSelfServiceVisitor
Batch sync	<p>A role used for automatic batch synchronization of identities with external sources such as Active Directory. This role can not be assigned to persons, but only used for this purpose.</p> <p>For the batch synchronization to work, the following entry must be set in the <i>system.properties</i> file of the prime explorer:</p> <pre>batchSync.permissionRole=BaseRoleBatchSync</pre>	PRIME Designer: No PRIME Explorer: No	BaseRoleBatchSync

Bootstrap users

The following bootstrap users are defined in PRIME, to quickly get started. These must be removed after setting up the system.

Username	Role	Password
admin	BaseRoleBootstrapAdmin	admin
approver	BaseRoleOfficer ScmRoleApproverOfficer	approver
consultant	BaseRolePolicyAdmin	consultant
helpdesk	BaseRoleHelpDeskOfficer	helpdesk
requester	BaseRoleRegistrationOfficer BaseRoleProductionAdmin BaseRoleIssuingAuthority ScmRoleServerRegistrationOfficer ScmRoleServerAdministrator	requester
service	BaseRoleServiceAdmin	service
useradmin	BaseRoleUserAdmin	useradmin